

CAMWorks Solids 2008 Installation Issue

Back to: AmeriCAM Corp.com

The following problems have occurred with some installations of CAMWorks Solids 2008 from the DVD or a download:

- During installation, a log file displays indicating a problem with the installation.
- No error or warning messages display during installation, but CAMWorks Solids is unable to start. After double-clicking the icon to start, it appears as if nothing is happening.

If either of these occur, try these steps:

1. Go to Start -> Control Panel -> Add or Remove Programs .
2. Remove the following:

CAMWorks Solids 2008
Microsoft .NET Framework 3.0
Microsoft Visual C++ 2005 Redistributable

3. Reboot the system.
4. Reinstall the .Net Framework 3.0 component.

The .Net Framework 3.0 component install is on the CAMWorks 2008 DVD in the \camworks2008solids\swwi\data\DotNetFx folder. Run the dotnetfx3.exe program for Windows XP Pro. Note that dotnetfx3_x64.exe is for 64 bit OS.

5. Reinstall the Visual C++ 2005 Redistributable component.

The Visual C++ 2005 Redistributable component install is on the CAMWorks 2008 DVD in the \camworks2008solids\swwi\data\VCRedist folder. Run the vcredist_x86.exe program.

6. Reboot the System.
7. Open My Computer, delete the folder that CAMWorks Solids 2008 was installed in (e.g., C:\program files\CAMWorks Solids 2008)
8. Reinstall CAMWorks Solids.

Back to: AmeriCAM Corp.com